

AerMonitor AM-1015 for WinXP



There are two steps to do:


1. Flash PIXCIR for WinXP
2. Install PIXCIR HID driver

Unzip "XP-Touch Driver and Calibration.zip"


1. Flash PIXCIR for WinXP




Run HID_Download_V2.7.exe




select "Setting" Button and remember the Version "0x1107"
select "Switch to COM"




select path, where "manbo_driver.inf" is located
"C:\Documents and Settings\Administrator\My Documents\XP-Touch Driver and Calibration\XP-Touch Driver and Calibration"






When finish, go ahead below.





select **EEPROM Pixcir File** "OPEN"


select: "AUO_15inch_20120403_3mm_Firich_code_out.eep.pix"



select **EEPROM Pixcir File "DOWNLOAD"**



select: "SWITCH TO HID"





Clean your Touch Glass and select "Calibrate"

Close "PIXCIR Control Deskwork" and install the PIXCIR HID Driver

2. Install PIXCIR HID Driver



Run setup.exe



pixcir Setup [X]

User Information
Enter your user information and click Next to continue.

Name:

Company:

< Back Next > Cancel

pixcir Setup [X]



Installation Folder
Where would you like pixcir to be installed?




The software will be installed in the folder listed below. To select a different location, either type in a new path, or click Change to browse for an existing folder.

Install pixcir to:


Space required: 86.5 KB
Space available on selected drive: 54.30 GB

< Back Next > Cancel





Check your device manager



Close Windows and reboot

3.12.2012 Fe

Novopos AG